Package 'pense'

October 3, 2020

Type Package

Title Penalized Elastic Net S/MM-Estimator of Regression

Version 2.0.2

Date 2020-10-03

Copyright See the file COPYRIGHT for copyright details on some of the functions and algorithms used.

Encoding UTF-8

Biarch true

SystemRequirements C++11

URL https://dakep.github.io/pense-rpkg, https://github.com/dakep/pense-rpkg

BugReports https://github.com/dakep/pense-rpkg/issues

Description Robust penalized (adaptive) elastic net S and M estimators for linear regression. The methods are proposed in Cohen Freue, G. V., Kepplinger, D., Salibián-Barrera, M., and Smucler, E. (2019) <https://projecteuclid.org/euclid.aoas/1574910036>. The package implements the extensions and algorithms described in Kepplinger, D. (2020) <doi:10.14288/1.0392915>.

Depends R (>= 3.5.0), Matrix

Imports Rcpp, methods, parallel, lifecycle (>= 0.2.0), rlang (>= 0.4.0)

LinkingTo Rcpp, RcppArmadillo (>= 0.9.600)

Suggests testthat (>= 2.1.0), knitr, rmarkdown

License MIT + file LICENSE

NeedsCompilation yes

RoxygenNote 7.1.1

Roxygen list(markdown = TRUE, load = ``source")

RdMacros lifecycle

VignetteBuilder knitr

R **topics documented:**

---

coef.pense_cvfit *Extract Coefficient Estimates*

Description

Extract coefficients from a PENSE (or LS-EN) regularization path with hyper-parameters chosen by cross-validation.

Usage

```
## S3 method for class 'pense_cvfit'
coef(
  object,
  lambda = c("min", "se"),
  se_mult = 1,
  sparse = NULL,
  exact = deprecated(),
  correction = deprecated(),
  ...
)
```

Arguments

object	PENSE with cross-validated hyper-parameters to extract coefficients from.
lambda	either a string specifying which penalty level to use ("min" or "se") or a a single numeric value of the penalty parameter. See details.
se_mult	If lambda = "se", the multiple of standard errors to tolerate.
sparse	should coefficients be returned as sparse or dense vectors? Defaults to the sparse argument supplied to [pense_cv()](). Can also be set to sparse = 'matrix', in which case a sparse matrix is returned instead of a sparse vector.
exact	deprecated. Always gives a warning if lambda is not part of the fitted sequence and coefficients are interpolated.
correction	defunct.
...	currently not used.

Details

If lambda = "se" and object contains fitted estimates for every penalization level in the sequence, extract the coefficients of the most parsimonious model with prediction performance statistically indistinguishable from the best model. This is determined to be the model with prediction performance within se_mult * cv_se from the best model.

Value

either a numeric vector or a sparse vector of type [dsparseVector]() of size $p + 1$, depending on the sparse argument. Note: prior to version 2.0.0 sparse coefficients were returned as sparse matrix of type *dgCMatrix*. To get a sparse matrix, use sparse = 'matrix'.

See Also

Other functions for extracting components: coef.pense_fit(), predict.pense_cvfit(), predict.pense_fit(), residuals.pense_cvfit(), residuals.pense_fit()

Examples

```
# Compute the PENSE regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- pense(x, freeny$y, alpha = 0.5)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[40])

# What penalization level leads to good prediction performance?
cv_results <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4)
plot(cv_results, se_mult = 1)

# Extract the coefficients at the penalization level with
# smallest prediction error ...
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

coef.pense_fit   *Extract Coefficient Estimates*

Description

Extract coefficients from a PENSE (or LS-EN) regularization path fitted by pense() or elnet().

Usage

```
## S3 method for class 'pense_fit'
coef(
  object,
  lambda,
  sparse = NULL,
  exact = deprecated(),
  correction = deprecated(),
  ...
)
```

Arguments

object	PENSE regularization path to extract coefficients from.
lambda	a single value of the penalty parameter.

sparse	should coefficients be returned as sparse or dense vectors? Defaults to the sparse argument supplied to [pense()](). Can also be set to sparse = 'matrix', in which case a sparse matrix is returned instead of a sparse vector.
exact	defunct Always gives a warning if lambda is not part of the fitted sequence and hence coefficients are interpolated.
correction	defunct.
...	currently not used.

Value

either a numeric vector or a sparse vector of type [dsparseVector]() of size $p + 1$, depending on the sparse argument. Note: prior to version 2.0.0 sparse coefficients were returned as sparse matrix of type *dgCMatrix*. To get a sparse matrix, use sparse = 'matrix'.

See Also

[coef.pense_cvfit()]() for extracting coefficients from a PENSE fit with hyper-parameters chosen by cross-validation

Other functions for extracting components: [coef.pense_cvfit]()(), [predict.pense_cvfit]()(), [predict.pense_fit]()(), [residuals.pense_cvfit]()(), [residuals.pense_fit]()()

Examples

```
# Compute the PENSE regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- pense(x, freeny$y, alpha = 0.5)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[40])

# What penalization level leads to good prediction performance?
cv_results <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4)
plot(cv_results, se_mult = 1)

# Extract the coefficients at the penalization level with
# smallest prediction error ...
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

consistency_const   *Get the Constant for Consistency for the M-Scale*

Description

Get the Constant for Consistency for the M-Scale

Usage

```
consistency_const(delta, rho)
```

Arguments

delta	desired breakdown point (between 0 and 0.5)
rho	the name of the chosen ρ function.

Value

consistency constant

See Also

Other miscellaneous functions: [rho_function()](rho_function)

---

deprecated_en_options   *Deprecated*

Description

Deprecated

Options for computing EN estimates.

Usage

```
en_options_aug_lars(use_gram = c("auto", "yes", "no"), eps = 1e-12)

en_options_dal(
  maxit = 100,
  eps = 1e-08,
  eta_mult = 2,
  eta_start_numerator = 0.01,
  eta_start,
  preconditioner = c("approx", "none", "diagonal"),
  verbosity = 0
)
```

Arguments

use_gram	**ignored.** Should the Gram matrix be pre-computed.
eps	**ignored.** Numeric tolerance for convergence.
maxit	maximum number of iterations allowed.
eta_mult	multiplier to increase eta at each iteration.
eta_start_numerator	
	if eta_start is missing, it is defined by eta_start = eta_start_numerator / lambda.
eta_start	**ignored.** The start value for eta.
preconditioner	**ignored.** Preconditioner for the numerical solver. If none, a standard solver will be used, otherwise the faster preconditioned conjugate gradient is used.
verbosity	**ignored.**

Functions

- en_options_aug_lars: Superseded by `en_lars_options()`.

- en_options_dal: Superseded by `en_dal_options()`

Warning

Do not use these functions in new code. They may be removed from future versions of the package.

See Also

Other deprecated functions: `enpy()`, `initest_options()`, `mstep_options()`, `pense_options()`, `pensem()`

---

elnet   *Compute the Least Squares (Adaptive) Elastic Net Regularization Path*

Description

Compute least squares EN estimates for linear regression with optional observation weights and penalty loadings.

Usage

```
elnet(
  x,
  y,
  alpha,
  nlambda = 100,
  lambda_min_ratio,
  lambda,
  penalty_loadings,
  weights,
  intercept = TRUE,
  en_algorithm_opts,
  sparse = FALSE,
  eps = 1e-06,
  standardize = TRUE,
  correction = deprecated(),
  xtest = deprecated(),
  options = deprecated()
)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
alpha	elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
nlambda	number of penalization levels.

lambda_min_ratio

        Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and `alpha`. If more observations than variables are available, the default is `1e-3 * alpha`, otherwise `1e-2 * alpha`.

lambda   optional user-supplied sequence of penalization levels. If given and not `NULL`, `nlambda` and `lambda_min_ratio` are ignored.

penalty_loadings

        a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient.

weights   a vector of positive observation weights.

intercept   include an intercept in the model.

en_algorithm_opts

        options for the EN algorithm. See [en_algorithm_options](#) for details.

sparse   use sparse coefficient vectors.

eps   numerical tolerance.

standardize   standardize variables to have unit variance. Coefficients are always returned in original scale.

correction   defunct. Correction for EN estimates is not supported anymore.

xtest   deprecated. Instead, extract coefficients with [coef.pense_fit()](#) and compute predictions manually.

options   deprecated. Use `en_algorithm_opts` instead.

Details

The elastic net estimator for the linear regression model solves the optimization problem

$$argmin_{\mu,\beta}(1/2n) \sum_i w_i(y_i - \mu - x'_i\beta)^2 + \lambda \sum_j 0.5(1-\alpha)\beta_j^2 + \alpha l_j|\beta_j|$$

with observation weights w_i and penalty loadings l_j.

Value

a list-like object with the following items

lambda the sequence of penalization parameters.

estimates a list of estimates. Each estimate contains the following information:

    intercept intercept estimate.

    beta beta (slope) estimate.

    lambda penalization level at which the estimate is computed.

    alpha *alpha* hyper-parameter at which the estimate is computed.

    statuscode if > 0 the algorithm experienced issues when computing the estimate.

    status optional status message from the algorithm.

call the original call.

predictions if `xtest` was given, a matrix of predicted values. Each column corresponds to the predictions from the estimate at the `lambda` value at the same index.

See Also

`pense()` for an S-estimate of regression with elastic net penalty.

`coef.pense_fit()` for extracting coefficient estimates.

`plot.pense_fit()` for plotting the regularization path.

Other functions for computing non-robust estimates: `elnet_cv()`

Examples

```
# Compute the LS-EN regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- elnet(x, freeny$y, alpha = 0.75)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[5])

# What penalization level leads to good prediction performance?
cv_results <- elnet_cv(x, freeny$y, alpha = 0.75, cv_repl = 10,
                       cv_k = 4, cv_measure = 'tau')
plot(cv_results, se_mult = 1)
plot(cv_results, se_mult = 1, what = 'coef.path')

# Extract the coefficients at the penalization level with
# smallest prediction error ...
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

elnet_cv   *Cross-validation for Least-Squares (Adaptive) Elastic Net Estimates*

Description

Perform (repeated) K-fold cross-validation for `elnet()`.

Usage

```
elnet_cv(
  x,
  y,
  lambda,
  cv_k,
  cv_repl = 1,
  cv_metric = c("rmspe", "tau_size", "mape", "auroc"),
  fit_all = TRUE,
  cl = NULL,
  ncores = deprecated(),
  ...
)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
lambda	optional user-supplied sequence of penalization levels. If given and not NULL, nlambda and lambda_min_ratio are ignored.
cv_k	number of folds per cross-validation.
cv_repl	number of cross-validation replications.
cv_metric	either a string specifying the performance metric to use, or a function to evaluate prediction errors in a single CV replication. If a function, the number of arguments define the data the function receives. If the function takes a single argument, it is called with a single numeric vector of prediction errors. If the function takes two or more arguments, it is called with the predicted values as first argument and the true values as second argument. The function must always return a single numeric value quantifying the prediction performance. The order of the given values corresponds to the order in the input data.
fit_all	If TRUE, fit the model for all penalization levels. Otherwise, only at penalization level with smallest average CV performance.
cl	a [parallel](#) cluster. Can only be used if ncores = 1, because multi-threading can not be used in parallel R sessions on the same host.
ncores	deprecated and not used anymore.
...	Arguments passed on to [elnet](#)
	alpha elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
	nlambda number of penalization levels.
	lambda_min_ratio Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and alpha. If more observations than variables are available, the default is 1e-3 * alpha, otherwise 1e-2 * alpha.
	penalty_loadings a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient.
	standardize standardize variables to have unit variance. Coefficients are always returned in original scale.
	weights a vector of positive observation weights.
	intercept include an intercept in the model.
	sparse use sparse coefficient vectors.
	en_algorithm_opts options for the EN algorithm. See [en_algorithm_options](#) for details.
	eps numerical tolerance.
	xtest deprecated. Instead, extract coefficients with [coef.pense_fit()](#) and compute predictions manually.
	options deprecated. Use en_algorithm_opts instead.
	correction defunct. Correction for EN estimates is not supported anymore.

Details

The built-in CV metrics are

"tau_size" τ-size of the prediction error, computed by [tau_size()](default).

"mape" Median absolute prediction error.

"rmspe" Root mean squared prediction error.

"auroc" Area under the receiver operator characteristic curve (actually 1 - AUROC). Only sensible for binary responses.

Value

a list with components:

lambda the sequence of penalization levels.

cvres data frame of average cross-validated performance.

cv_replications matrix of cross-validated performance metrics, one column per replication. Rows are in the same order as in cvres.

call the original call.

estimates the estimates fitted on the full data. Same format as returned by [elnet()](#).

See Also

[elnet()](#) for computing the LS-EN regularization path without cross-validation.

[pense_cv()](#) for cross-validation of S-estimates of regression with elastic net penalty.

[coef.pense_cvfit()](#) for extracting coefficient estimates.

[plot.pense_cvfit()](#) for plotting the CV performance or the regularization path.

Other functions for computing non-robust estimates: [elnet()](#)

Examples

```
# Compute the LS-EN regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- elnet(x, freeny$y, alpha = 0.75)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[5])

# What penalization level leads to good prediction performance?
cv_results <- elnet_cv(x, freeny$y, alpha = 0.75, cv_repl = 10,
                       cv_k = 4, cv_measure = 'tau')
plot(cv_results, se_mult = 1)
plot(cv_results, se_mult = 1, what = 'coef.path')

# Extract the coefficients at the penalization level with
# smallest prediction error ...
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

enpy   *Deprecated*

Description

Deprecated

Compute initial estimates for EN S-estimates using ENPY. Superseded by enpy_initial_estimates().

Usage

```
enpy(x, y, alpha, lambda, delta, cc, options, en_options)
```

Arguments

x	data matrix with predictors.
y	response vector.
alpha, lambda	EN penalty parameters (NOT adjusted for the number of observations in x).
delta	desired breakdown point of the resulting estimator.
cc	tuning constant for the S-estimator. Default is to chosen based on the breakdown point delta. Should never have to be changed.
options	**ignored.** Additional options for the initial estimator.
en_options	**ignored.** Additional options for the EN algorithm.

Value

coeff	A numeric matrix with one initial coefficient per column
objF	A vector of values of the objective function for the respective coefficient

Warning

Do not use this function in new code. It may be removed from future versions of the package.

See Also

Other deprecated functions: deprecated_en_options, initest_options(), mstep_options(), pense_options(), pensem()

---

enpy_initial_estimates

ENPY Initial Estimates for EN S-Estimators

Description

Compute initial estimates for the EN S-estimator using the EN-PY procedure.

Usage

```
enpy_initial_estimates(
  x,
  y,
  alpha,
  lambda,
  bdp = 0.25,
  cc,
  intercept = TRUE,
  penalty_loadings,
  enpy_opts = enpy_options(),
  mscale_opts = mscale_algorithm_options(),
  eps = 1e-06,
  sparse = FALSE,
  ncores = 1L
)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n.
alpha	elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
lambda	a vector of positive values of penalization levels.
bdp	desired breakdown point of the estimator, between 0 and 0.5.
cc	cutoff value for the bisquare rho function. By default, chosen to yield a consistent estimate for the Normal distribution.
intercept	include an intercept in the model.
penalty_loadings	
	a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.
enpy_opts	options for the EN-PY algorithm, created with the enpy_options() function.
mscale_opts	options for the M-scale estimation. See mscale_algorithm_options() for details.
eps	numerical tolerance.
sparse	use sparse coefficient vectors.
ncores	number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.

Details

If these manually computed initial estimates are intended as starting points for pense(), they are by default *shared* for all penalization levels. To restrict the use of the initial estimates to the penalty level they were computed for, use as_starting_point(...,specific = TRUE). See as_starting_point() for details.

References

Cohen Freue, G.V.; Kepplinger, D.; Salibián-Barrera, M.; Smucler, E. Robust elastic net estimators for variable selection and identification of proteomic biomarkers. *Ann. Appl. Stat.* **13** (2019), no. 4, 2065–2090 doi: 10.1214/19AOAS1269

See Also

Other functions for initial estimates: prinsens(), starting_point()

---

enpy_options   *Options for the ENPY Algorithm*

Description

Additional control options for the elastic net Peña-Yohai procedure.

Usage

```
enpy_options(
  max_it = 10,
  keep_psc_proportion = 0.5,
  en_algorithm_opts,
  keep_residuals_measure = c("threshold", "proportion"),
  keep_residuals_proportion = 0.5,
  keep_residuals_threshold = 2,
  retain_best_factor = 2,
  retain_max = 500
)
```

Arguments

max_it   maximum number of EN-PY iterations.

keep_psc_proportion

                    how many observations should to keep based on the Principal Sensitivity Components.

en_algorithm_opts

                    options for the LS-EN algorithm. See en_algorithm_options for details.

keep_residuals_measure

                    how to determine what observations to keep, based on their residuals. If proportion, a fixed number of observations is kept. If threshold, only observations with residuals below the threshold are kept.

keep_residuals_proportion

                    proportion of observations to kept based on their residuals.

```
keep_residuals_threshold
```
only observations with (standardized) residuals less than this threshold are kept.

```
retain_best_factor
```
only keep candidates that are within this factor of the best candidate. If <= 1, only keep candidates from the last iteration.

```
retain_max
```
maximum number of candidates, i.e., only the best `retain_max` candidates are retained.

Details

The EN-PY procedure for computing initial estimates iteratively cleans the data of observations with possibly outlying residual or high leverage. Least-squares elastic net (LS-EN) estimates are computed on the possibly clean subsets. At each iteration, the Principal Sensitivity Components are computed to remove observations with potentially high leverage. Among all the LS-EN estimates, the estimate with smallest M-scale of the residuals is selected. Observations with largest residual for the selected estimate are removed and the next iteration is started.

Value

options for the ENPY algorithm.

---

en_admm_options   *Use the ADMM Elastic Net Algorithm*

Description

Use the ADMM Elastic Net Algorithm

Usage

```
en_admm_options(max_it = 1000, step_size, acceleration = 1)
```

Arguments

`max_it`	maximum number of iterations.
`step_size`	step size for the algorithm.
`acceleration`	acceleration factor for linearized ADMM.

Value

options for the ADMM EN algorithm.

See Also

Other EN algorithms: `en_dal_options()`, `en_lars_options()`

en_algorithm_options   *Control the Algorithm to Compute (Weighted) Least-Squares Elastic Net Estimates*

Description

The package supports different algorithms to compute the EN estimate for weighted LS loss functions. Each algorithm has certain characteristics that make it useful for some problems. To select a specific algorithm and adjust the options, use any of the en_***_options functions.

Details

- `en_lars_options()`: Use the tuning-free LARS algorithm. This computes *exact* (up to numerical errors) solutions to the EN-LS problem. It is not iterative and therefore can not benefit from approximate solutions, but in turn guarantees that a solution will be found.

- `en_admm_options()`: Use an iterative ADMM-type algorithm which needs $O(np)$ operations per iteration and converges sub-linearly.

- `en_dal_options()`: Use the iterative Dual Augmented Lagrangian (DAL) method. DAL needs $O(n^3 p^2)$ operations per iteration, but converges exponentially.

---

en_dal_options   *Use the DAL Elastic Net Algorithm*

Description

Use the DAL Elastic Net Algorithm

Usage

```
en_dal_options(
  max_it = 100,
  max_inner_it = 100,
  eta_multiplier = 2,
  eta_start_conservative = 0.01,
  eta_start_aggressive = 1,
  lambda_relchange_aggressive = 0.25
)
```

Arguments

max_it   maximum number of (outer) iterations.

max_inner_it   maximum number of (inner) iterations in each outer iteration.

eta_multiplier   multiplier for the barrier parameter. In each iteration, the barrier must be more restrictive (i.e., the multiplier must be > 1).

eta_start_conservative

         conservative initial barrier parameter. This is used if the previous penalty is undefined or too far away.

eta_start_aggressive

         aggressive initial barrier parameter. This is used if the previous penalty is close.

lambda_relchange_aggressive

         how close must the lambda parameter from the previous penalty term be to use an aggressive initial barrier parameter (i.e., what constitutes "too far").

Value

options for the DAL EN algorithm.

See Also

Other EN algorithms: `en_admm_options()`, `en_lars_options()`

---

  en_lars_options   *Use the LARS Elastic Net Algorithm*

Description

Use the LARS Elastic Net Algorithm

Usage

```
en_lars_options()
```

See Also

Other EN algorithms: `en_admm_options()`, `en_dal_options()`

---

  initest_options   *Deprecated*

Description

Deprecated

Options for computing initial estimates via ENPY. Superseded by `enpy_options()`.

Usage

```
initest_options(
  keep_solutions = 5,
  psc_method = c("exact", "rr"),
  maxit = 10,
  maxit_pense_refinement = 5,
  eps = 1e-06,
  psc_keep = 0.5,
  resid_keep_method = c("proportion", "threshold"),
  resid_keep_prop = 0.6,
  resid_keep_thresh = 2,
  mscale_eps = 1e-08,
  mscale_maxit = 200
)
```

Arguments

keep_solutions	how many initial estimates should be kept to perform full PENSE iterations?
psc_method	The method to use for computing the principal sensitivity components. See details for the possible choices.
maxit	maximum number of refinement iterations.
maxit_pense_refinement	
	ignored. Maximum number of PENSE iterations to refine initial estimator.
eps	**ignored.** Numeric tolerance for convergence.
psc_keep	proportion of observations to keep based on the PSC scores.
resid_keep_method	
	How to clean the data based on large residuals. If "proportion", observations with the smallest resid_keep_prop residuals will be retained. If "threshold", all observations with scaled residuals smaller than the threshold resid_keep_thresh will be retained.
resid_keep_prop, resid_keep_thresh	
	proportion or threshold for observations to keep based on their residual.
mscale_eps, mscale_maxit	
	ignored. Maximum number of iterations and numeric tolerance for the M-scale.

Warning

Do not use this function in new code. It may be removed from future versions of the package.

See Also

Other deprecated functions: deprecated_en_options, enpy(), mstep_options(), pense_options(), pensem()

---

mloc	*Compute the M-estimate of Location*

Description

Compute the M-estimate of location using an auxiliary estimate of the scale.

Usage

```
mloc(x, scale, rho, cc, opts = mscale_algorithm_options())
```

Arguments

x	numeric values. Missing values are verbosely ignored.
scale	scale of the x values. If omitted, uses the mad().
rho	the ρ function to use. See rho_function() for available functions.
cc	value of the tuning constant for the chosen ρ function. By default, chosen to achieve 95% efficiency under the Normal distribution.
opts	a list of options for the M-estimating algorithm, see mscale_algorithm_options() for details.

Value

a single numeric value, the M-estimate of location.

See Also

Other functions to compute robust estimates of location and scale: mlocscale(), mscale(), tau_size()

---

mlocscale	*Compute the M-estimate of Location and Scale*

Description

Simultaneous estimation of the location and scale by means of M-estimates.

Usage

```
mlocscale(
  x,
  bdp = 0.25,
  scale_cc = consistency_const(bdp, "bisquare"),
  location_rho,
  location_cc,
  opts = mscale_algorithm_options()
)
```

Arguments

x	numeric values. Missing values are verbosely ignored.
bdp	desired breakdown point (between 0 and 0.5).
scale_cc	cutoff value for the bisquare ρ function for computing the scale estimate. By default, chosen to yield a consistent estimate for normally distributed values.
location_rho, location_cc	
	ρ function and cutoff value for computing the location estimate. See rho_function() for a list of available ρ functions.
opts	a list of options for the M-estimating equation, see mscale_algorithm_options() for details.

Value

a vector with 2 elements, the M-estimate of location and the M-scale estimate.

See Also

Other functions to compute robust estimates of location and scale: mloc(), mscale(), tau_size()

---

mm_algorithm_options   *MM-Algorithm to Compute Penalized Elastic Net S- and M-Estimates*

Description

Additional options for the MM algorithm to compute EN S- and M-estimates.

Usage

```
mm_algorithm_options(
  max_it = 500,
  tightening = c("adaptive", "exponential", "none"),
  tightening_steps = 10,
  en_algorithm_opts
)
```

Arguments

max_it   maximum number of iterations.

tightening   how to make inner iterations more precise as the algorithm approaches a local
                    minimum.

tightening_steps
                    for *adaptive* tightening strategy, how often to tighten until the desired tolerance
                    is attained.

en_algorithm_opts
                    options for the inner LS-EN algorithm. See en_algorithm_options for details.

Value

options for the MM algorithm.

---

mscale   *Compute the M-Scale of Centered Values*

Description

Compute the M-scale without centering the values.

Usage

```
mscale(
  x,
  bdp = 0.25,
  cc = consistency_const(bdp, "bisquare"),
  opts = mscale_algorithm_options(),
  delta = deprecated(),
  rho = deprecated(),
  eps = deprecated(),
  maxit = deprecated()
)
```

Arguments

x	numeric values. Missing values are verbosely ignored.
bdp	desired breakdown point (between 0 and 0.5).
cc	cutoff value for the bisquare rho function. By default, chosen to yield a consistent estimate for the Normal distribution.
opts	a list of options for the M-scale estimation algorithm, see `mscale_algorithm_options()` for details.
delta	deprecated. Use bpd instead.
rho, eps, maxit	deprecated. Instead set control options for the algorithm with the `opts` arguments.

Value

the M-estimate of scale.

See Also

Other functions to compute robust estimates of location and scale: `mlocscale()`, `mloc()`, `tau_size()`

---

mscale_algorithm_options

Options for the M-scale Estimation Algorithm

Description

Options for the M-scale Estimation Algorithm

Usage

```
mscale_algorithm_options(max_it = 200, eps = 1e-08)
```

Arguments

max_it	maximum number of iterations.
eps	numerical tolerance to check for convergence.

Value

options for the M-scale estimation algorithm.

---

mstep_options *Deprecated*

Description

Deprecated

Additional options for computing penalized EN MM-estimates. Superseded by `mm_algorithm_options()` and options supplied directly to `pensem_cv()`.

Usage

```
mstep_options(
  cc = 3.44,
  maxit = 1000,
  eps = 1e-06,
  adjust_bdp = FALSE,
  verbosity = 0,
  en_correction = TRUE
)
```

Arguments

cc   **ignored.** Tuning constant for the M-estimator.

maxit   maximum number of iterations allowed.

eps   **ignored.** Numeric tolerance for convergence.

adjust_bdp   **ignored.** Should the breakdown point be adjusted based on the effective degrees of freedom?

verbosity   **ignored.** Verbosity of the algorithm.

en_correction **ignored.** Should the corrected EN estimator be used to choose the optimal lambda with CV. If `TRUE`, as by default, the estimator is "bias corrected".

Warning

Do not use this function in new code. It may be removed from future versions of the package.

See Also

Other deprecated functions: `deprecated_en_options`, `enpy()`, `initest_options()`, `pense_options()`, `pensem()`

---

pense   *Compute (Adaptive) Elastic Net S-Estimates of Regression*

Description

Compute elastic net S-estimates (PENSE estimates) along a grid of penalization levels with optional penalty loadings for adaptive elastic net.

Usage

```
pense(
  x,
  y,
  alpha,
  nlambda = 50,
  nlambda_enpy = 10,
  lambda,
  lambda_min_ratio,
  enpy_lambda,
  penalty_loadings,
  intercept = TRUE,
  bdp = 0.25,
  cc,
  add_zero_based = TRUE,
  enpy_specific = FALSE,
  other_starts,
  eps = 1e-06,
  explore_solutions = 10,
  explore_tol = 0.1,
  max_solutions = 10,
  comparison_tol = sqrt(eps),
  sparse = FALSE,
  ncores = 1,
  standardize = TRUE,
  algorithm_opts = mm_algorithm_options(),
  mscale_opts = mscale_algorithm_options(),
  enpy_opts = enpy_options(),
  cv_k = deprecated(),
  cv_objective = deprecated(),
  ...
)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
alpha	elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
nlambda	number of penalization levels.

nlambda_enpy	number of penalization levels where the EN-PY initial estimate is computed.
lambda	optional user-supplied sequence of penalization levels. If given and not NULL, nlambda and lambda_min_ratio are ignored.
lambda_min_ratio	
	Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and alpha. If more observations than variables are available, the default is 1e-3 * alpha, otherwise 1e-2 * alpha.
enpy_lambda	optional user-supplied sequence of penalization levels at which EN-PY initial estimates are computed. If given and not NULL, nlambda_enpy is ignored.
penalty_loadings	
	a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.
intercept	include an intercept in the model.
bdp	desired breakdown point of the estimator, between 0 and 0.5.
cc	tuning constant for the S-estimator. Default is to chosen based on the breakdown point bdp. Does *not* affect the estimated coefficients, only the estimated scale of the residuals.
add_zero_based	also consider the 0-based regularization path. See details for a description.
enpy_specific	use the EN-PY initial estimates only at the penalization level they are computed for. See details for a description.
other_starts	a list of other staring points, created by [starting_point()](). If the output of [enpy_initial_estimates()]() is given, the starting points will be *shared* among all penalization levels. Note that if a the starting point is *specific* to a penalization level, this penalization level is added to the grid of penalization levels (either the manually specified grid in lambda or the automatically generated grid of size nlambda). If standardize = TRUE, the starting points are also scaled.
eps	numerical tolerance.
explore_solutions	
	number of solutions to compute up to the desired precision eps.
explore_tol	numerical tolerance for exploring possible solutions. Should be (much) looser than eps to be useful.
max_solutions	only retain up to max_solutions unique solutions per penalization level.
comparison_tol	numeric tolerance to determine if two solutions are equal. The comparison is first done on the absolute difference in the value of the objective function at the solution If this is less than comparison_tol, two solutions are deemed equal if the squared difference of the intercepts is less than comparison_tol and the squared L_2 norm of the difference vector is less than comparison_tol.
sparse	use sparse coefficient vectors.
ncores	number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.
standardize	logical flag to standardize the x variables prior to fitting the PENSE estimates. Coefficients are always returned on the original scale. This can fail for variables with a large proportion of a single value (e.g., zero-inflated data). In this case, either compute with standardize = FALSE or standardize the data manually.
algorithm_opts	options for the MM algorithm to compute the estimates. See [mm_algorithm_options()]() for details.

mscale_opts	options for the M-scale estimation. See [mscale_algorithm_options()](#) for details.
enpy_opts	options for the ENPY initial estimates, created with the [enpy_options()](#) function. See [enpy_initial_estimates()](#) for details.
cv_k, cv_objective	
	deprecated and ignored. See [pense_cv()](#) for estimating prediction performance via cross-validation.
...	ignored. See the section on deprecated parameters below.

Value

a list-like object with the following items

lambda the sequence of penalization levels.

estimates a list of estimates. Each estimate contains the following information:

> intercept intercept estimate.
>
> beta beta (slope) estimate.
>
> lambda penalization level at which the estimate is computed.
>
> alpha *alpha* hyper-parameter at which the estimate is computed.
>
> objf_value value of the objective function at the solution.
>
> statuscode if > 0 the algorithm experienced issues when computing the estimate.
>
> status optional status message from the algorithm.

call the original call.

Strategies for Using Starting Points

The function supports several different strategies to compute, and use the provided starting points for optimizing the PENSE objective function.

Starting points are computed internally but can also be supplied via other_starts. By default, starting points are computed internally by the EN-PY procedure for penalization levels supplied in enpy_lambda (or the automatically generated grid of length nlambda_enpy). By default, starting points computed by the EN-PY procedure are *shared* for all penalization levels in lambda (or the automatically generated grid of length nlambda). If the starting points should be *specific* to the penalization level the starting points' penalization level, set the enpy_specific argument to TRUE.

In addition to EN-PY initial estimates, the algorithm can also use the "0-based" strategy if add_zero_based = TRUE (by default). Here, the 0-vector is used to start the optimization at the largest penalization level in lambda. At subsequent penalization levels, the solution at the previous penalization level is also used as starting point.

At every penalization level, all starting points are explored using the loose numerical tolerance explore_tol. Only the best explore_solutions are computed to the stringent numerical tolerance eps. Finally, only the best max_solutions are retained and carried forward as starting points for the subsequent penalization level.

Deprecated Arguments

Starting with version 2.0.0, cross-validation is performed by separate function [pense_cv()](#). Arguments related cross-validation cause an error when supplied to pense(). Furthermore, the following arguments are deprecated as of version 2.0.0: initial, warm_reset, cl, options, init_options, en_options. If pense() is called with any of these arguments, warnings detail how to replace them.

See Also

pense_cv() for selecting hyper-parameters via cross-validation.

coef.pense_fit() for extracting coefficient estimates.

plot.pense_fit() for plotting the regularization path.

Other functions to compute robust estimates: regmest()

Examples

```
# Compute the PENSE regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- pense(x, freeny$y, alpha = 0.5)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[40])

# What penalization level leads to good prediction performance?
cv_results <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4)
plot(cv_results, se_mult = 1)

# Extract the coefficients at the penalization level with
# smallest prediction error ...
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

pensem   *Deprecated Alias of pensem_cv*

Description

pensem() is a deprecated alias for pensem_cv().

Usage

```
pensem(x, ...)
```

Arguments

x   either a numeric matrix of predictor values, or a cross-validated PENSE fit from
             pense_cv().

...   ignored. See the section on deprecated parameters below.

See Also

Other deprecated functions: deprecated_en_options, enpy(), initest_options(), mstep_options(),
pense_options()

---

pensem_cv   *Compute Penalized Elastic Net M-Estimates from PENSE*

Description

This is a convenience wrapper around pense_cv() and regmest_cv(), for the common use-case
of computing a highly-robust S-estimate followed by a more efficient M-estimate using the scale of
the residuals from the S-estimate.

Usage

```
pensem_cv(x, ...)

## Default S3 method:
pensem_cv(
  x,
  y,
  alpha = 0.5,
  nlambda = 50,
  lambda_min_ratio,
  lambda_m,
  lambda_s,
  standardize = TRUE,
  penalty_loadings,
  intercept = TRUE,
  bdp = 0.25,
  ncores = 1,
  sparse = FALSE,
  eps = 1e-06,
  cc = 4.7,
  cv_k = 5,
  cv_repl = 1,
  cl = NULL,
  cv_metric = c("tau_size", "mape", "rmspe"),
  add_zero_based = TRUE,
  explore_solutions = 10,
  explore_tol = 0.1,
  max_solutions = 10,
  fit_all = TRUE,
  comparison_tol = sqrt(eps),
  algorithm_opts = mm_algorithm_options(),
  mscale_opts = mscale_algorithm_options(),
  nlambda_enpy = 10,
  enpy_opts = enpy_options(),
  ...
)

## S3 method for class 'pense_cvfit'
pensem_cv(
  x,
  scale,
```

```
  alpha,
  nlambda = 50,
  lambda_min_ratio,
  lambda_m,
  standardize = TRUE,
  penalty_loadings,
  intercept = TRUE,
  bdp = 0.25,
  ncores = 1,
  sparse = FALSE,
  eps = 1e-06,
  cc = 4.7,
  cv_k = 5,
  cv_repl = 1,
  cl = NULL,
  cv_metric = c("tau_size", "mape", "rmspe"),
  add_zero_based = TRUE,
  explore_solutions = 10,
  explore_tol = 0.1,
  max_solutions = 10,
  fit_all = TRUE,
  comparison_tol = sqrt(eps),
  algorithm_opts = mm_algorithm_options(),
  mscale_opts = mscale_algorithm_options(),
  x_train,
  y_train,
  ...
)
```

Arguments

x	either a numeric matrix of predictor values, or a cross-validated PENSE fit from [pense_cv()]().
...	ignored. See the section on deprecated parameters below.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
alpha	elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
nlambda	number of penalization levels.
lambda_min_ratio	
	Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and alpha. If more observations than variables are available, the default is 1e-3 * alpha, otherwise 1e-2 * alpha.
lambda_m, lambda_s	
	optional user-supplied sequence of penalization levels for the S- and M-estimates. If given and not NULL, nlambda and lambda_min_ratio are ignored for the respective estimate (S and/or M).
standardize	logical flag to standardize the x variables prior to fitting the PENSE estimates. Coefficients are always returned on the original scale. This can fail for variables

with a large proportion of a single value (e.g., zero-inflated data). In this case, either compute with standardize = FALSE or standardize the data manually.

penalty_loadings

a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.

intercept   include an intercept in the model.

bdp   desired breakdown point of the estimator, between 0 and 0.5.

ncores   number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.

sparse   use sparse coefficient vectors.

eps   numerical tolerance.

cc   cutoff constant for Tukey's bisquare ρ function in the M-estimation objective function.

cv_k   number of folds per cross-validation.

cv_repl   number of cross-validation replications.

cl   a [parallel](#) cluster. Can only be used if ncores = 1, because multi-threading can not be used in parallel R sessions on the same host.

cv_metric   either a string specifying the performance metric to use, or a function to evaluate prediction errors in a single CV replication. If a function, the number of arguments define the data the function receives. If the function takes a single argument, it is called with a single numeric vector of prediction errors. If the function takes two or more arguments, it is called with the predicted values as first argument and the true values as second argument. The function must always return a single numeric value quantifying the prediction performance. The order of the given values corresponds to the order in the input data.

add_zero_based   also consider the 0-based regularization path. See details for a description.

explore_solutions

number of solutions to compute up to the desired precision eps.

explore_tol   numerical tolerance for exploring possible solutions. Should be (much) looser than eps to be useful.

max_solutions   only retain up to max_solutions unique solutions per penalization level.

fit_all   If TRUE, fit the model for all penalization levels. Otherwise, only at penalization level with smallest average CV performance.

comparison_tol   numeric tolerance to determine if two solutions are equal. The comparison is first done on the absolute difference in the value of the objective function at the solution If this is less than comparison_tol, two solutions are deemed equal if the squared difference of the intercepts is less than comparison_tol and the squared L_2 norm of the difference vector is less than comparison_tol.

algorithm_opts   options for the MM algorithm to compute the estimates. See [mm_algorithm_options()](#) for details.

mscale_opts   options for the M-scale estimation. See [mscale_algorithm_options()](#) for details.

nlambda_enpy   number of penalization levels where the EN-PY initial estimate is computed.

enpy_opts   options for the ENPY initial estimates, created with the [enpy_options()](#) function. See [enpy_initial_estimates()](#) for details.

scale   initial scale estimate to use in the M-estimation. By default the S-scale from the
                        PENSE fit is used.

x_train, y_train
                        override arguments x and y as provided in the call to pense_cv(). This is useful
                        if the arguments in the pense_cv() call are not available in the current environ-
                        ment.

Details

The built-in CV metrics are

"tau_size" τ-size of the prediction error, computed by [tau_size()](#) (default).

"mape" Median absolute prediction error.

"rmspe" Root mean squared prediction error.

"auroc" Area under the receiver operator characteristic curve (actually 1 - AUROC). Only sensible
         for binary responses.

Value

an object of cross-validated regularized M-estimates as returned from [regmest_cv()](#).

See Also

[pense_cv()](#) to compute the starting S-estimate.

Other functions to compute robust estimates with CV: [pense_cv()](#), [regmest_cv()](#)

---

pense_cv   *Cross-validation for (Adaptive) PENSE Estimates*

Description

Perform (repeated) K-fold cross-validation for [pense()](#).

adapense_cv() is a convenience wrapper to compute adaptive PENSE estimates.

Usage

```
pense_cv(
  x,
  y,
  standardize = TRUE,
  lambda,
  cv_k,
  cv_repl = 1,
  cv_metric = c("tau_size", "mape", "rmspe", "auroc"),
  fit_all = TRUE,
  cl = NULL,
  ...
)

adapense_cv(x, y, alpha, alpha_preliminary = 0, exponent = 1, ...)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
standardize	whether to standardize the x variables prior to fitting the PENSE estimates. Can also be set to "cv_only", in which case the input data is not standardized, but the training data in the CV folds is scaled to match the scaling of the input data. Coefficients are always returned on the original scale. This can fail for variables with a large proportion of a single value (e.g., zero-inflated data). In this case, either compute with standardize = FALSE or standardize the data manually.
lambda	optional user-supplied sequence of penalization levels. If given and not NULL, nlambda and lambda_min_ratio are ignored.
cv_k	number of folds per cross-validation.
cv_repl	number of cross-validation replications.
cv_metric	either a string specifying the performance metric to use, or a function to evaluate prediction errors in a single CV replication. If a function, the number of arguments define the data the function receives. If the function takes a single argument, it is called with a single numeric vector of prediction errors. If the function takes two or more arguments, it is called with the predicted values as first argument and the true values as second argument. The function must always return a single numeric value quantifying the prediction performance. The order of the given values corresponds to the order in the input data.
fit_all	If TRUE, fit the model for all penalization levels. Otherwise, only at penalization level with smallest average CV performance.
cl	a [parallel](#) cluster. Can only be used if ncores = 1, because multi-threading can not be used in parallel R sessions on the same host.
...	Arguments passed on to [pense](#)

            nlambda number of penalization levels.

            lambda_min_ratio Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and alpha. If more observations than variables are available, the default is 1e-3 * alpha, otherwise 1e-2 * alpha.

            nlambda_enpy number of penalization levels where the EN-PY initial estimate is computed.

            penalty_loadings a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.

            enpy_lambda optional user-supplied sequence of penalization levels at which EN-PY initial estimates are computed. If given and not NULL, nlambda_enpy is ignored.

            other_starts a list of other staring points, created by [starting_point()](#). If the output of [enpy_initial_estimates()](#) is given, the starting points will be *shared* among all penalization levels. Note that if a the starting point is *specific* to a penalization level, this penalization level is added to the grid of penalization levels (either the manually specified grid in lambda or the automatically generated grid of size nlambda). If standardize = TRUE, the starting points are also scaled.

            intercept include an intercept in the model.

bdp   desired breakdown point of the estimator, between 0 and 0.5.

cc   tuning constant for the S-estimator. Default is to chosen based on the breakdown point bdp. Does *not* affect the estimated coefficients, only the estimated scale of the residuals.

eps   numerical tolerance.

explore_solutions   number of solutions to compute up to the desired precision eps.

explore_tol   numerical tolerance for exploring possible solutions. Should be (much) looser than eps to be useful.

max_solutions   only retain up to max_solutions unique solutions per penalization level.

comparison_tol   numeric tolerance to determine if two solutions are equal. The comparison is first done on the absolute difference in the value of the objective function at the solution If this is less than comparison_tol, two solutions are deemed equal if the squared difference of the intercepts is less than comparison_tol and the squared L_2 norm of the difference vector is less than comparison_tol.

add_zero_based   also consider the 0-based regularization path. See details for a description.

enpy_specific   use the EN-PY initial estimates only at the penalization level they are computed for. See details for a description.

sparse   use sparse coefficient vectors.

ncores   number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.

algorithm_opts   options for the MM algorithm to compute the estimates. See mm_algorithm_options() for details.

mscale_opts   options for the M-scale estimation. See mscale_algorithm_options() for details.

enpy_opts   options for the ENPY initial estimates, created with the enpy_options() function. See enpy_initial_estimates() for details.

cv_objective   deprecated and ignored. See pense_cv() for estimating prediction performance via cross-validation.

alpha   elastic net penalty mixing parameter with $0 \le \alpha \le 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.

alpha_preliminary

              alpha parameter for the preliminary estimate.

exponent   the exponent for computing the penalty loadings based on the preliminary estimate.

Details

The built-in CV metrics are

"tau_size" τ-size of the prediction error, computed by tau_size() (default).

"mape"   Median absolute prediction error.

"rmspe"   Root mean squared prediction error.

"auroc"   Area under the receiver operator characteristic curve (actually 1 - AUROC). Only sensible for binary responses.

adapense_cv() is a convenience wrapper which performs 3 steps:

1. compute preliminary estimates via pense_cv(...,alpha = alpha_preliminary),
2. computes the penalty loadings from the estimate beta with best prediction performance by adapense_loadings = 1 / abs(beta)^exponent, and
3. compute the adaptive PENSE estimates via pense_cv(...,penalty_loadings = adapense_loadings).

Value

a list with components:

lambda the sequence of penalization levels.

cvres data frame of average cross-validated performance.

cv_replications matrix of cross-validated performance metrics, one column per replication. Rows are in the same order as in cvres.

call the original call.

estimates the estimates fitted on the full data. Same format as returned by [pense()](#).

the object returned by adapense_cv() has additional components

preliminary the CV results for the preliminary estimate.

penalty_loadings the penalty loadings used for the adaptive PENSE estimate.

See Also

[pense()](#) for computing regularized S-estimates without cross-validation.

[coef.pense_cvfit()](#) for extracting coefficient estimates.

[plot.pense_cvfit()](#) for plotting the CV performance or the regularization path.

Other functions to compute robust estimates with CV: [pensem_cv()](#), [regmest_cv()](#)

Other functions to compute robust estimates with CV: [pensem_cv()](#), [regmest_cv()](#)

Examples

```
# Compute the adaptive PENSE regularization path for Freeny's
# revenue data (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

## Either use the convenience function directly ...
ada_convenience <- adapense_cv(x, freeny$y, alpha = 0.5,
                               cv_repl = 2, cv_k = 4)

## ... or compute the steps manually:
# Step 1: Compute preliminary estimates with CV
preliminary_estimate <- pense_cv(x, freeny$y, alpha = 0,
                                 cv_repl = 2, cv_k = 4)
plot(preliminary_estimate, se_mult = 1)

# Step 2: Use the coefficients with best prediction performance
# to define the penalty loadings:
prelim_coefs <- coef(preliminary_estimate, lambda = 'min')
pen_loadings <- 1 / abs(prelim_coefs[-1])
```

```
# Step 3: Compute the adaptive PENSE estimates and estimate
# their prediction performance.
ada_manual <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4, penalty_loadings = pen_loadings)

# Visualize the prediction performance and coefficient path of
# the adaptive PENSE estimates (manual vs. automatic)
def.par <- par(no.readonly = TRUE)
layout(matrix(1:4, ncol = 2, byrow = TRUE))
plot(ada_convenience$preliminary)
plot(preliminary_estimate)
plot(ada_convenience)
plot(ada_manual)
par(def.par)
```

---

pense_options   *Deprecated*

Description

Deprecated

Additional options for computing penalized EN S-estimates. Superseded by [mm_algorithm_options()](#)
and options supplied directly to [pense()](#).

Usage

```
pense_options(
  delta = 0.25,
  maxit = 1000,
  eps = 1e-06,
  mscale_eps = 1e-08,
  mscale_maxit = 200,
  verbosity = 0,
  cc = NULL,
  en_correction = TRUE
)
```

Arguments

delta	desired breakdown point of the resulting estimator.
maxit	maximum number of iterations allowed.
eps	numeric tolerance for convergence.
mscale_eps, mscale_maxit	
	maximum number of iterations and numeric tolerance for the M-scale.
verbosity	**ignored.** Verbosity of the algorithm.
cc	**ignored.** Tuning constant for the S-estimator. Default is to chosen based on the breakdown point delta. Should never have to be changed.
en_correction	**ignored.** Should the corrected EN estimator be used to choose the optimal lambda with CV. If TRUE, as by default, the estimator is "bias corrected".

Warning

Do not use this function in new code. It may be removed from future versions of the package.

See Also

Other deprecated functions: deprecated_en_options, enpy(), initest_options(), mstep_options(), pensem()

---

plot.pense_cvfit   *Plot Method for Penalized Estimates With Cross-Validation*

Description

Plot the cross-validation performance or the coefficient path for fitted penalized elastic net S- or LS-estimates of regression.

Usage

```
## S3 method for class 'pense_cvfit'
plot(x, what = c("cv", "coef.path"), se_mult = 1, ...)
```

Arguments

x	fitted estimates with cross-validation information.
what	plot either the CV performance or the coefficient path.
se_mult	if plotting CV performance, multiplier of the estimated SE.
...	currently ignored.

See Also

Other functions for plotting and printing: plot.pense_fit(), prediction_performance(), summary.pense_cvfit()

Examples

```
# Compute the PENSE regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- pense(x, freeny$y, alpha = 0.5)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[40])

# What penalization level leads to good prediction performance?
cv_results <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4)
plot(cv_results, se_mult = 1)

# Extract the coefficients at the penalization level with
# smallest prediction error ...
```

```
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

plot.pense_fit   *Plot Method for Penalized Estimates*

Description

Plot the coefficient path for fitted penalized elastic net S- or LS-estimates of regression.

Usage

```
## S3 method for class 'pense_fit'
plot(x, ...)
```

Arguments

x   fitted estimates.

...   currently ignored.

See Also

Other functions for plotting and printing: plot.pense_cvfit(), prediction_performance(),
summary.pense_cvfit()

Examples

```
# Compute the PENSE regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- pense(x, freeny$y, alpha = 0.5)
plot(regpath)

# Extract the coefficients at a certain penalization level
coef(regpath, lambda = regpath$lambda[40])

# What penalization level leads to good prediction performance?
cv_results <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4)
plot(cv_results, se_mult = 1)

# Extract the coefficients at the penalization level with
# smallest prediction error ...
coef(cv_results)
# ... or at the penalization level with prediction error
# statistically indistinguishable from the minimum.
coef(cv_results, lambda = 'se')
```

---

predict.pense_cvfit   *Predict Method for PENSE Fits*

Description

Predict response values using a PENSE (or LS-EN) regularization path with hyper-parameters chosen by cross-validation.

Usage

```
## S3 method for class 'pense_cvfit'
predict(
  object,
  newdata,
  lambda = c("min", "se"),
  se_mult = 1,
  exact = deprecated(),
  correction = deprecated(),
  ...
)
```

Arguments

object	PENSE with cross-validated hyper-parameters to extract coefficients from.
newdata	an optional matrix of new predictor values. If missing, the fitted values are computed.
lambda	either a string specifying which penalty level to use or a a single numeric value of the penalty parameter. See details.
se_mult	If lambda = "se", the multiple of standard errors to tolerate.
exact	deprecated. Always gives a warning if lambda is not part of the fitted sequence and coefficients are interpolated.
correction	defunct.
...	currently not used.

Details

If lambda = "se" and object contains fitted estimates for every penalization level in the sequence, extract the residuals of the most parsimonious model with prediction performance statistically indistinguishable from the best model. This is determined to be the model with prediction performance within se_mult * cv_se from the best model.

Value

a numeric vector of residuals for the given penalization level.

See Also

Other functions for extracting components: coef.pense_cvfit(), coef.pense_fit(), predict.pense_fit(), residuals.pense_cvfit(), residuals.pense_fit()

Examples

```
# Compute the LS-EN regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- elnet(x, freeny$y, alpha = 0.75)

# Predict the response using a specific penalization level
predict(regpath, newdata = freeny[1:5, 2:5],
        lambda = regpath$lambda[10])

# Extract the residuals at a certain penalization level
residuals(regpath, lambda = regpath$lambda[5])

# Select penalization level via cross-validation
cv_results <- elnet_cv(x, freeny$y, alpha = 0.5, cv_repl = 10,
                       cv_k = 4)

# Predict the response using the "best" penalization level
predict(cv_results, newdata = freeny[1:5, 2:5])

# Extract the residuals at the "best" penalization level
residuals(cv_results)^2
# Extract the residuals at a more parsimonious penalization level
residuals(cv_results, lambda = 'se')
```

---

predict.pense_fit   *Predict Method for PENSE Fits*

Description

Predict response values using a PENSE (or LS-EN) regularization path fitted by [pense()](#) or [elnet()](#).

Usage

```
## S3 method for class 'pense_fit'
predict(
  object,
  newdata,
  lambda,
  exact = deprecated(),
  correction = deprecated(),
  ...
)
```

Arguments

object	PENSE regularization path to extract residuals from.
newdata	an optional matrix of new predictor values. If missing, the fitted values are computed.
lambda	a single value of the penalty parameter.

exact	defunct Always gives a warning if lambda is not part of the fitted sequence and coefficients need to be interpolated.
correction	defunct.
...	currently not used.

Value

a numeric vector of residuals for the given penalization level.

See Also

Other functions for extracting components: coef.pense_cvfit(), coef.pense_fit(), predict.pense_cvfit(), residuals.pense_cvfit(), residuals.pense_fit()

Examples

```
# Compute the LS-EN regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- elnet(x, freeny$y, alpha = 0.75)

# Predict the response using a specific penalization level
predict(regpath, newdata = freeny[1:5, 2:5],
        lambda = regpath$lambda[10])

# Extract the residuals at a certain penalization level
residuals(regpath, lambda = regpath$lambda[5])

# Select penalization level via cross-validation
cv_results <- elnet_cv(x, freeny$y, alpha = 0.5, cv_repl = 10,
                       cv_k = 4)

# Predict the response using the "best" penalization level
predict(cv_results, newdata = freeny[1:5, 2:5])

# Extract the residuals at the "best" penalization level
residuals(cv_results)^2
# Extract the residuals at a more parsimonious penalization level
residuals(cv_results, lambda = 'se')
```

---

prediction_performance

Prediction Performance of Adaptive PENSE Fits

Description

Extract the prediction performance of one or more (adaptive) PENSE fits.

Usage

```
prediction_performance(..., lambda = c("min", "se"), se_mult = 1)

## S3 method for class 'pense_pred_perf'
print(x, ...)
```

Arguments

`...`	one or more (adaptive) PENSE fits with cross-validation information.
`lambda`	a string specifying which penalty level to use ("min" or "se") . See details.
`se_mult`	If `lambda = "se"`, the multiple of standard errors to tolerate.
`x`	an object with information on prediction performance created with `prediction_performance()`.

Details

If `lambda = "se"` and the cross-validation was performed with multiple replications, use the penalty level whit prediction performance within `se_mult` of the best prediction performance.

Value

a data frame with details about the prediction performance of the given PENSE fits. The data frame has a custom print method summarizing the prediction performances.

See Also

[summary.pense_cvfit()](#) for a summary of the fitted model.

Other functions for plotting and printing: [plot.pense_cvfit()](#), [plot.pense_fit()](#), [summary.pense_cvfit()](#)

---

prinsens	*Principal Sensitivity Components*

Description

Compute Principal Sensitivity Components for Elastic Net Regression

Usage

```
prinsens(
  x,
  y,
  alpha,
  lambda,
  intercept = TRUE,
  penalty_loadings,
  en_algorithm_opts,
  eps = 1e-06,
  sparse = FALSE,
  ncores = 1L,
  method = deprecated()
)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n.
alpha	elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
lambda	optional user-supplied sequence of penalization levels. If given and not NULL, nlambda and lambda_min_ratio are ignored.
intercept	include an intercept in the model.
penalty_loadings	a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.
en_algorithm_opts	options for the LS-EN algorithm. See en_algorithm_options for details.
eps	numerical tolerance.
sparse	use sparse coefficient vectors.
ncores	number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.
method	defunct. PSCs are always computed for EN estimates. For the PY procedure for unpenalized estimation use package pyinit.

Value

a list of principal sensitivity components, one per element in lambda. Each PSC is itself a list with items lambda, alpha, and pscs.

References

Cohen Freue, G.V.; Kepplinger, D.; Salibián-Barrera, M.; Smucler, E. Robust elastic net estimators for variable selection and identification of proteomic biomarkers. *Ann. Appl. Stat.* **13** (2019), no. 4, 2065–2090 doi: 10.1214/19AOAS1269

Pena, D., and Yohai, V.J. A Fast Procedure for Outlier Diagnostics in Large Regression Problems. *J. Amer. Statist. Assoc.* **94** (1999). no. 446, 434–445. doi: 10.2307/2670164

See Also

Other functions for initial estimates: enpy_initial_estimates(), starting_point()

---

regmest	*Compute (Adaptive) Elastic Net M-Estimates of Regression*

Description

Compute elastic net M-estimates along a grid of penalization levels with optional penalty loadings for adaptive elastic net.

Usage

```
regmest(
  x,
  y,
  alpha,
  nlambda = 50,
  lambda,
  lambda_min_ratio,
  scale,
  starting_points,
  penalty_loadings,
  intercept = TRUE,
  cc = 4.7,
  eps = 1e-06,
  explore_solutions = 10,
  explore_tol = 0.1,
  max_solutions = 10,
  comparison_tol = sqrt(eps),
  sparse = FALSE,
  ncores = 1,
  standardize = TRUE,
  algorithm_opts = mm_algorithm_options(),
  add_zero_based = TRUE,
  mscale_bdp = 0.25,
  mscale_opts = mscale_algorithm_options()
)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
alpha	elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. alpha = 1 is the LASSO penalty, and alpha = 0 the Ridge penalty.
nlambda	number of penalization levels.
lambda	optional user-supplied sequence of penalization levels. If given and not NULL, nlambda and lambda_min_ratio are ignored.
lambda_min_ratio	
	Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and alpha. If more observations than variables are available, the default is 1e-3 * alpha, otherwise 1e-2 * alpha.
scale	fixed scale of the residuals.
starting_points	
	a list of staring points, created by [starting_point()](). The starting points are shared among all penalization levels.
penalty_loadings	
	a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.

intercept	include an intercept in the model.
cc	cutoff constant for Tukey's bisquare ρ function.
eps	numerical tolerance.
explore_solutions	
	number of solutions to compute up to the desired precision eps.
explore_tol	numerical tolerance for exploring possible solutions. Should be (much) looser than eps to be useful.
max_solutions	only retain up to max_solutions unique solutions per penalization level.
comparison_tol	numeric tolerance to determine if two solutions are equal. The comparison is first done on the absolute difference in the value of the objective function at the solution If this is less than comparison_tol, two solutions are deemed equal if the squared difference of the intercepts is less than comparison_tol and the squared L_2 norm of the difference vector is less than comparison_tol.
sparse	use sparse coefficient vectors.
ncores	number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.
standardize	logical flag to standardize the x variables prior to fitting the M-estimates. Coefficients are always returned on the original scale. This can fail for variables with a large proportion of a single value (e.g., zero-inflated data). In this case, either compute with standardize = FALSE or standardize the data manually.
algorithm_opts	options for the MM algorithm to compute estimates. See mm_algorithm_options() for details.
add_zero_based	also consider the 0-based regularization path in addition to the given starting points.
mscale_bdp, mscale_opts	
	options for the M-scale estimate used to standardize the predictors (if standardize = TRUE).

Value

a list-like object with the following items

lambda the sequence of penalization levels.

scale the used scale of the residuals.

estimates a list of estimates. Each estimate contains the following information:

    intercept intercept estimate.

    beta beta (slope) estimate.

    lambda penalization level at which the estimate is computed.

    alpha *alpha* hyper-parameter at which the estimate is computed.

    objf_value value of the objective function at the solution.

    statuscode if > 0 the algorithm experienced issues when computing the estimate.

    status optional status message from the algorithm.

call the original call.

See Also

[regmest_cv()](#) for selecting hyper-parameters via cross-validation.

[coef.pense_fit()](#) for extracting coefficient estimates.

[plot.pense_fit()](#) for plotting the regularization path.

Other functions to compute robust estimates: [pense](#)()

---

regmest_cv   *Cross-validation for (Adaptive) Elastic Net M-Estimates*

Description

Perform (repeated) K-fold cross-validation for [regmest()](#).

adamest_cv() is a convenience wrapper to compute adaptive elastic-net M-estimates.

Usage

```
regmest_cv(
  x,
  y,
  standardize = TRUE,
  lambda,
  cv_k,
  cv_repl = 1,
  cv_metric = c("tau_size", "mape", "rmspe", "auroc"),
  fit_all = TRUE,
  cl = NULL,
  ...
)

adamest_cv(x, y, alpha, alpha_preliminary = 0, exponent = 1, ...)
```

Arguments

x	n by p matrix of numeric predictors.
y	vector of response values of length n. For binary classification, y should be a factor with 2 levels.
standardize	whether to standardize the x variables prior to fitting the PENSE estimates. Can also be set to "cv_only", in which case the input data is not standardized, but the training data in the CV folds is scaled to match the scaling of the input data. Coefficients are always returned on the original scale. This can fail for variables with a large proportion of a single value (e.g., zero-inflated data). In this case, either compute with standardize = FALSE or standardize the data manually.
lambda	optional user-supplied sequence of penalization levels. If given and not NULL, nlambda and lambda_min_ratio are ignored.
cv_k	number of folds per cross-validation.
cv_repl	number of cross-validation replications.

cv_metric	either a string specifying the performance metric to use, or a function to evaluate prediction errors in a single CV replication. If a function, the number of arguments define the data the function receives. If the function takes a single argument, it is called with a single numeric vector of prediction errors. If the function takes two or more arguments, it is called with the predicted values as first argument and the true values as second argument. The function must always return a single numeric value quantifying the prediction performance. The order of the given values corresponds to the order in the input data.
fit_all	If TRUE, fit the model for all penalization levels. Otherwise, only at penalization level with smallest average CV performance.
cl	a [parallel] cluster. Can only be used if ncores = 1, because multi-threading can not be used in parallel R sessions on the same host.
...	Arguments passed on to [regmest]

    scale fixed scale of the residuals.

    nlambda number of penalization levels.

    lambda_min_ratio Smallest value of the penalization level as a fraction of the largest level (i.e., the smallest value for which all coefficients are zero). The default depends on the sample size relative to the number of variables and alpha. If more observations than variables are available, the default is 1e-3 * alpha, otherwise 1e-2 * alpha.

    penalty_loadings a vector of positive penalty loadings (a.k.a. weights) for different penalization of each coefficient. Only allowed for alpha > 0.

    starting_points a list of staring points, created by [starting_point()]. The starting points are shared among all penalization levels.

    intercept include an intercept in the model.

    add_zero_based also consider the 0-based regularization path in addition to the given starting points.

    cc cutoff constant for Tukey's bisquare ρ function.

    eps numerical tolerance.

    explore_solutions number of solutions to compute up to the desired precision eps.

    explore_tol numerical tolerance for exploring possible solutions. Should be (much) looser than eps to be useful.

    max_solutions only retain up to max_solutions unique solutions per penalization level.

    comparison_tol numeric tolerance to determine if two solutions are equal. The comparison is first done on the absolute difference in the value of the objective function at the solution If this is less than comparison_tol, two solutions are deemed equal if the squared difference of the intercepts is less than comparison_tol and the squared L_2 norm of the difference vector is less than comparison_tol.

    sparse use sparse coefficient vectors.

    ncores number of CPU cores to use in parallel. By default, only one CPU core is used. May not be supported on your platform, in which case a warning is given.

    algorithm_opts options for the MM algorithm to compute estimates. See [mm_algorithm_options()] for details.

    mscale_bdp options for the M-scale estimate used to standardize the predictors (if standardize = TRUE).

                  `mscale_opts` options for the M-scale estimate used to standardize the predic-
                      tors (if `standardize = TRUE`).

`alpha`   elastic net penalty mixing parameter with $0 \leq \alpha \leq 1$. `alpha = 1` is the LASSO
                      penalty, and `alpha = 0` the Ridge penalty.

`alpha_preliminary`
                  `alpha` parameter for the preliminary estimate.

`exponent`   the exponent for computing the penalty loadings based on the preliminary esti-
                      mate.

Details

The built-in CV metrics are

`"tau_size"` τ-size of the prediction error, computed by [tau_size()](#) (default).

`"mape"` Median absolute prediction error.

`"rmspe"` Root mean squared prediction error.

`"auroc"` Area under the receiver operator characteristic curve (actually 1 - AUROC). Only sensible
for binary responses.

`adamest_cv()` is a convenience wrapper which performs 3 steps:

1. compute preliminary estimates via `regmest_cv(...,alpha = alpha_preliminary)`,

2. computes the penalty loadings from the estimate `beta` with best prediction performance by
   `adamest_loadings = 1 / abs(beta)^exponent`, and

3. compute the adaptive PENSE estimates via `regmest_cv(...,penalty_loadings = adamest_loadings)`.

Value

a list with components:

`lambda` the sequence of penalization levels.

`scale` the used scale of the residuals.

`cvres` data frame of average cross-validated performance.

`cv_replications` matrix of cross-validated performance metrics, one column per replication.
Rows are in the same order as in `cvres`.

`call` the original call.

`estimates` the estimates fitted on the full data. Same format as returned by [regmest()](#).

the object returned by `adamest_cv()` has additional components

`preliminary` the CV results for the preliminary estimate.

`penalty_loadings` the penalty loadings used for the adaptive elastic net M-estimate.

See Also

[regmest()](#) for computing regularized S-estimates without cross-validation.

[coef.pense_cvfit()](#) for extracting coefficient estimates.

[plot.pense_cvfit()](#) for plotting the CV performance or the regularization path.

Other functions to compute robust estimates with CV: [pense_cv()](#), [pensem_cv()](#)

Other functions to compute robust estimates with CV: [pense_cv()](#), [pensem_cv()](#)

Examples

```
# Compute the adaptive PENSE regularization path for Freeny's
# revenue data (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

## Either use the convenience function directly ...
ada_convenience <- adapense_cv(x, freeny$y, alpha = 0.5,
                               cv_repl = 2, cv_k = 4)

## ... or compute the steps manually:
# Step 1: Compute preliminary estimates with CV
preliminary_estimate <- pense_cv(x, freeny$y, alpha = 0,
                                 cv_repl = 2, cv_k = 4)
plot(preliminary_estimate, se_mult = 1)

# Step 2: Use the coefficients with best prediction performance
# to define the penality loadings:
prelim_coefs <- coef(preliminary_estimate, lambda = 'min')
pen_loadings <- 1 / abs(prelim_coefs[-1])

# Step 3: Compute the adaptive PENSE estimates and estimate
# their prediction performance.
ada_manual <- pense_cv(x, freeny$y, alpha = 0.5, cv_repl = 2,
                       cv_k = 4, penalty_loadings = pen_loadings)

# Visualize the prediction performance and coefficient path of
# the adaptive PENSE estimates (manual vs. automatic)
def.par <- par(no.readonly = TRUE)
layout(matrix(1:4, ncol = 2, byrow = TRUE))
plot(ada_convenience$preliminary)
plot(preliminary_estimate)
plot(ada_convenience)
plot(ada_manual)
par(def.par)
```

---

residuals.pense_cvfit *Extract Residuals*

Description

Extract residuals from a PENSE (or LS-EN) regularization path with hyper-parameters chosen by cross-validation.

Usage

```
## S3 method for class 'pense_cvfit'
residuals(
  object,
  lambda = c("min", "se"),
  se_mult = 1,
  exact = deprecated(),
  correction = deprecated(),
```

```
    ...
)
```

Arguments

object	PENSE with cross-validated hyper-parameters to extract coefficients from.
lambda	either a string specifying which penalty level to use or a a single numeric value of the penalty parameter. See details.
se_mult	If lambda = "se", the multiple of standard errors to tolerate.
exact	deprecated. Always gives a warning if lambda is not part of the fitted sequence and coefficients are interpolated.
correction	defunct.
...	currently not used.

Details

If lambda = "se" and object contains fitted estimates for every penalization level in the sequence, extract the residuals of the most parsimonious model with prediction performance statistically indistinguishable from the best model. This is determined to be the model with prediction performance within se_mult * cv_se from the best model.

Value

a numeric vector of residuals for the given penalization level.

See Also

Other functions for extracting components: coef.pense_cvfit(), coef.pense_fit(), predict.pense_cvfit(), predict.pense_fit(), residuals.pense_fit()

Examples

```
# Compute the LS-EN regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- elnet(x, freeny$y, alpha = 0.75)

# Predict the response using a specific penalization level
predict(regpath, newdata = freeny[1:5, 2:5],
        lambda = regpath$lambda[10])

# Extract the residuals at a certain penalization level
residuals(regpath, lambda = regpath$lambda[5])

# Select penalization level via cross-validation
cv_results <- elnet_cv(x, freeny$y, alpha = 0.5, cv_repl = 10,
                        cv_k = 4)

# Predict the response using the "best" penalization level
predict(cv_results, newdata = freeny[1:5, 2:5])

# Extract the residuals at the "best" penalization level
```

```
residuals(cv_results)^2
# Extract the residuals at a more parsimonious penalization level
residuals(cv_results, lambda = 'se')
```

---

residuals.pense_fit   *Extract Residuals*

Description

Extract residuals from a PENSE (or LS-EN) regularization path fitted by pense() or elnet().

Usage

```
## S3 method for class 'pense_fit'
residuals(object, lambda, exact = deprecated(), correction = deprecated(), ...)
```

Arguments

object	PENSE regularization path to extract residuals from.
lambda	a single value of the penalty parameter.
exact	defunct Always gives a warning if lambda is not part of the fitted sequence and coefficients need to be interpolated.
correction	defunct.
...	currently not used.

Value

a numeric vector of residuals for the given penalization level.

See Also

Other functions for extracting components: coef.pense_cvfit(), coef.pense_fit(), predict.pense_cvfit(), predict.pense_fit(), residuals.pense_cvfit()

Examples

```
# Compute the LS-EN regularization path for Freeny's revenue data
# (see ?freeny)
data(freeny)
x <- as.matrix(freeny[ , 2:5])

regpath <- elnet(x, freeny$y, alpha = 0.75)

# Predict the response using a specific penalization level
predict(regpath, newdata = freeny[1:5, 2:5],
        lambda = regpath$lambda[10])

# Extract the residuals at a certain penalization level
residuals(regpath, lambda = regpath$lambda[5])

# Select penalization level via cross-validation
cv_results <- elnet_cv(x, freeny$y, alpha = 0.5, cv_repl = 10,
```

```
                          cv_k = 4)

# Predict the response using the "best" penalization level
predict(cv_results, newdata = freeny[1:5, 2:5])

# Extract the residuals at the "best" penalization level
residuals(cv_results)^2
# Extract the residuals at a more parsimonious penalization level
residuals(cv_results, lambda = 'se')
```

---

rho_function   *List Available Rho Functions*

Description

List Available Rho Functions

Usage

```
rho_function(rho)
```

Arguments

rho   the name of the ρ function to check for existence.

Value

if rho is missing returns a vector of supported ρ function names, otherwise the internal integer
representation of the ρ function.

See Also

Other miscellaneous functions: [consistency_const](#)()

---

starting_point   *Create Starting Points for the PENSE Algorithm*

Description

Create a starting point for starting the PENSE algorithm in [pense()](#). Multiple starting points can
be created by combining starting points via c(starting_point_1,starting_point_2,...).

Usage

```
starting_point(beta, intercept, lambda)

as_starting_point(object, specific = FALSE, ...)

## S3 method for class 'enpy_starting_points'
as_starting_point(object, specific = FALSE, ...)

## S3 method for class 'pense_fit'
as_starting_point(object, specific = FALSE, lambda, ...)

## S3 method for class 'pense_cvfit'
as_starting_point(
  object,
  specific = FALSE,
  lambda = c("min", "se"),
  se_mult = 1,
  ...
)
```

Arguments

beta	beta coefficients at the starting point. Can be a numeric vector, a sparse vector of class dsparseVector, or a sparse matrix of class dgCMatrix with a single column.
intercept	intercept coefficient at the starting point.
lambda	optionally either a string specifying which penalty level to use ("min" or "se") or a numeric vector of the penalty levels to extract from object. Penalization levels not present in object are ignored with a warning. If NULL, all estimates in object are extracted.
object	an object with estimates to use as starting points.
specific	whether the estimates should be used as starting points only at the penalization level they are computed for. Defaults to using the estimates as starting points for all penalization levels.
...	further arguments passed to or from other methods.
se_mult	If lambda = "se", the multiple of standard errors to tolerate.

Details

A starting points can either be *shared*, i.e., used for every penalization level PENSE estimates are computed for, or *specific* to one penalization level. To create a specific starting point, provide the penalization level as lambda. If lambda is missing, a shared starting point is created. Shared and specific starting points can all be combined into a single list of starting points, with pense() handling them correctly. Note that specific starting points will lead to the lambda value being added to the grid of penalization levels. See pense() for details.

Starting points computed via enpy_initial_estimates() are by default *shared* starting points but can be transformed to *specific* starting points via enpy_starting_point(..., specific = TRUE).

When creating starting points from cross-validated fits, it is possible to extract only the estimate with best CV performance (lambda = "min"), or the estimate with CV performance statistically indistinguishable from the best performance (lambda = "se"). This is determined to be the estimate with prediction performance within se_mult * cv_se from the best model.

Value

an object of type starting_points to be used as starting point for pense().

See Also

Other functions for initial estimates: enpy_initial_estimates(), prinsens()

---

summary.pense_cvfit   *Summarize Cross-Validated PENSE Fit*

Description

If lambda = "se" and object contains fitted estimates for every penalization level in the sequence, extract the coefficients of the most parsimonious model with prediction performance statistically indistinguishable from the best model. This is determined to be the model with prediction performance within se_mult * cv_se from the best model.

Usage

```
## S3 method for class 'pense_cvfit'
summary(object, lambda = c("min", "se"), se_mult = 1, ...)

## S3 method for class 'pense_cvfit'
print(x, lambda = c("min", "se"), se_mult = 1, ...)
```

Arguments

object, x	an (adaptive) PENSE fit with cross-validation information.
lambda	either a string specifying which penalty level to use ("min" or "se") or a a single numeric value of the penalty parameter. See details.
se_mult	If lambda = "se", the multiple of standard errors to tolerate.
...	ignored.

See Also

prediction_performance() for information about the estimated prediction performance.

coef.pense_cvfit() for extracting only the estimated coefficients.

Other functions for plotting and printing: plot.pense_cvfit(), plot.pense_fit(), prediction_performance()

tau_size   *Compute the Tau-Scale of Centered Values*

Description

Compute the τ-scale without centering the values.

Usage

```
tau_size(x)
```

Arguments

x   numeric values. Missing values are verbosely ignored.

Value

the τ estimate of scale of centered values.

See Also

Other functions to compute robust estimates of location and scale: mlocscale(), mloc(), mscale()

Index